

# Instruction Manual

## Interface instruction

### NE216 progr. 01

---

## 1.1. General

The serial interface can accomplish the same functions as the display and the keyboard of the counter. It is possible to call up data and to change the programming of parameters. In general, the counter is controlled via a PC. However, it is also possible to use another device with similar features.

## 2. Transmission protocol

The transmission is effected character by character in ASCII code. Each character consists of 8 bits. The 8<sup>th</sup> bit is the parity bit, and in case of "no parity" it will always be sent as zero.

The counter responds to every request of the PC via the serial interface if the data has been correctly transmitted.

Character transmission is introduced with the start-of-text character <STX> and closed by the end-of-text character <ETX>. In addition, the counter sends a <CR> (carriage return) after <ETX>. This allows the input of a complete data block by means of one command (in high-level languages such as BASIC).

After <STX> there will follow an address allotted to the counter, making it possible to specifically address the counter within a serial network. After the address, please indicate the position that you wish to read out or to program. In case of a programming command, you will need to enter a "P" (for programming) and the data (parameters).

The protocol is classified into three groups as indicated below:

a) Read memory space (READ instruction):

```
<STX> identifier line <ETX> [<CR>]
```

b) Write memory location (WRITE instruction):

```
<STX> identifier line P data <ETX> [<CR>]
```

c) Special commands:

```
<STX> identifier parameters <ETX> [<CR>]
```

```
<STX>      Start of Text (02Hex)
Address    00...99 (device identifier)
Line       01...XX (see operating chart)
P          Programming command
Data       Parameter data
Parameter  Special commands
<ETX>     End of Text   (03Hex)
<CR>     0DHex (control token "carriage return")
          "CR" is optional but ever replied by the counter.
```

Example:

```
Standard  <STX> identifier line <ETX>      (identifier=35; line=02)
Ascii     <STX>3502<ETX>
Hex       02H, 33H, 35H, 30H, 32H, 03H
```

**Important!** The blanks between the particular characters of the commands only serve the purpose of better legibility. PC input must be without blanks. Control characters (less than 20Hex) are in "pointed" brackets. Any incorrect protocol received from the PC will be replied by an error message, provided NE216 remains still accessible. Please refer to chapter "Error messages" on page 4.

## 2. Reading of memory locations

All memory locations indexed with a line number in the programming scheme enable read out (except the separating lines that are indexed by dashes).

The protocol: <STX> Address Line <ETX> [<CR>] can be used for each line.

The counter response may vary in protocol length from one line to the other, since it depends on the data length of the respective memory location.

NE216 allows for read out both in RUN and PGM mode. The only difference lies in the counter response which will come with an "R" or a "P" in the mode parameter, as described in the following.

Response to a Read instruction (general):

```
<STX> identifier line mode data <ETX> <CR>

Mode      P= NE216 is in programming (PGM) mode
          R= NE216 is in RUN mode
VZ        Negative sign, only transferred with negative values
Data      max. total of digits, with preceding zeroes w/o decimal point
          (Exception: line 6 - with decimal point)
```

### 2.1. Examples for reading memory locations

The following applies to the examples below:

Counter address (Identifier) = 35; Counter mode = R (RUN-mode)

*Read main counter PC (line=01, displayed value =1500)*

Request: <STX>3501<ETX>

Reply: <STX>3501R001500<ETX><CR>

*Read scaling factor SF (line=07, parameter =1.0000)*

Request: <STX>3507<ETX>

Reply: <STX>3507R01.0000<ETX><CR>

*Read count mode (line =30, parameter = Pos. 3)*

Request: <STX>3530<ETX>

Reply: <STX>3530R3<ETX><CR> (3 meaning track A90°B single evaluation)

*Read device address (line=54, device address=35)*

Request: <STX>3554<ETX>

Reply: <STX>3554R35<ETX><CR>

### 3. Writing of memory locations

All memory locations indexed with a line number in the programming plan enable writing (programming), except for the separating lines (indexed by dashes) and lines 1 and 5.

Protocol: <STX> identifier line P [VZ] Data <ETX> [<CR>] can be applied to each line.

Counter response upon parameterization is the same as for a read command for the respective line.

Programming of memory locations is enabled both in RUN and PGM mode.

#### Programming in RUN mode:

**Parameterization in lines 21-23, 30-33, 35, 43, 44 and 51-54 will not become effective until a switching operation from PGM mode to RUN mode.** Please see chapter 5.2 for how to switch to PGM mode. The parameters in all other lines will be immediately effective after entry.

**Any parameterization done in RUN mode will only be retained non-volatile after having accomplished the switching operation from PGM to RUN mode. If omitted, the previously programmed parameters will be restored in the event of power failure.**

Write-command (general):

<STX> identifier line P [VZ] data <ETX> [<CR>]

#### 3.1. Examples for writing of memory locations

Following applies to the examples below:

Counter address (identifier) = 35; counter in mode = R (RUN)

*Programming the start count SC (line =04, start count=360)*

Command: <STX>3504P00360<ETX>

Response: <STX>3504R00360<ETX><CR>

*Programming a negative start count SC (line=04, start count=-360)*

Command: <STX>3504P-0360<ETX>

Response: <STX>3504R-0360<ETX><CR>

*Programming the scaling factor SF (line =07, parameter =1.0000)*

Command: <STX>3507P1.0000<ETX>

Response: <STX>3507R1.0000<ETX><CR>

*Programming the count mode (line =30, count mode=1)*

Command: <STX>3530P1<ETX>

Response: <STX>3530R1<ETX><CR>

*Programming the output time P1 at Latch(line=41)*

Command: <STX>3541PL<ETX>

Response: <STX>3541RL<ETX><CR>

*Programming the device identifier (line=54, device identifier=27)*

Command: <STX>3554P27<ETX>

Response: <STX>3554R27<ETX><CR>

## 4. Special commands

In the case of special commands, we are talking about instructions that do not refer to any line number (memory location on operator plan), with the exception of command "Clear current count".

### 4.1. Clear current count

The following special command will clear the current count PC (line 1). This line is disabled for parameterization. The remaining lines of the programming chart (except separating lines) are cleared by entering parameter 0 (as previously described in chapter 4).

The instruction to clear corresponds to a reset via C key. The counter response upon clearing is the same as with reading of the corresponding line.

General: <STX> address line <DEL> <ETX>

Example: Clear current count PC  
*Identifier =35, Line=01, Status=RUN mode*  
Command: <STX>3501<DEL><ETX>                   <DEL> = 7FHex  
Response: <STX>3501R00000<ETX><CR>

### 4.2. Switching the counter to PGM or RUN mode

This command allows you to switch the counter to and fro between PGM and RUN mode upon every data call. Both identifier and status are replied.

General: <STX> identifier <DC1> <ETX>

Example: *Identifier=35, Status=RUN mode, current line = 1, displayed value =15*  
Command: <STX>35<DC1><ETX>                   <DC1> = 11Hex  
Response: <STX>35P<ETX><CR>

Repeating the command will switch the counter back to RUN mode  
Command: <STX>35<DC1><ETX>  
Response: <STX>35R<ETX><CR>

### 4.3. Reading out the counter identification

Identification data are read only and will be followed by two parameters: Command parameter "I" (for identification) or selection parameter "T" (type and software number) or "D" (date and hardware version) for the several identification data.

Read out device type and software number:

*Address=35, Type =NE216, software number =01*  
Command: <STX>35IT<ETX>  
Response: <STX>35NE216 01<ETX><CR>

Read out date and version number:

*Address=35, Datum=02.10.96, version number=01*  
Command: <STX>35ID<ETX>  
Response: <STX>35021096 1<ETX><CR>

## 5. Error messages during data transfer

If receiving an invalid data protocol from the PC (for example line not existing or letters where there should be numbers) the counter – provided it is still accessible - will return a corresponding error message. To be able to do so, at least control character <STX> and identifier must be correct. If not, NE216 is no longer accessible and therefore not in a position to reply any error message to the PC.

In case no reply neither error message is replied on the PC request, it is a fatal error which means control character <STX> and identifier are missing. Furthermore, PC and NE216 interface parameters are not congruent. However these being correct, the failure is due to hardware or a defect in the data transmission line.

Standard structure in error messages:

<STX> Identifier line status <CAN> error number <ETX> <CR>

Example:     *Identifier =35, Line =09 (invalid line), error number =2*  
 <STX>3509R<CAN>2<ETX><CR>

The error message replied will come without „line“ and „status“ information.

Detailed error description:

Error 1: Format error (incorrect <ETX> position. This signal is given in case the data format was not kept during programming (for example during parameterization of a limit only 4 digits instead of 5 have been transferred).)

Error 2: Line (position) not existing or separating line

Error 3: Parameter error (invalid protocol data). Example: Scaling factor not only comprising numbers but also of other characters not permitted, or parameter beyond the permitted range.

## 6. Chart of the control characters applied

Control character	Hex	Decimal
<STX>	02	02
<ETX>	03	03
<ACK>	06	06
<LF>	0A	10
<CR>	0D	13
<DC1>	11	17
<CAN>	18	24
<DEL>	7F	127

## 7. Operating Plan

Line	Default	Customer pa-	Description
01	0		PC - current value displayed
02	1 0 0		P1 - preset 1
03	1 0 0 0		P2 - preset 2
04	0		SC - start count
05	0		tot - totalizer
07	1.0 0 0 0		SF - scaling factor
10	- - - - -		Separating line
11	S t a t 0	S t a t	PC - current value displayed
12	S t a t 0	S t a t	P1 - preset 1
13	S t a t 0	S t a t	P2 - preset 2
14	S t a t 2	S t a t	SC - start count
15	S t a t 2	S t a t	tot - totalizer
17	S t a t 2	S t a t	SF - scaling factor
20	- - - - -		Separating line
21	2 1 0	2 1	Operating mode
22	2 2 0	2 2	Preset mode
23	2 3 0	2 3	Reset
24	2 4 0	2 4	Decimal point in P1, P2, SC, tot
30	3 0 0	3 0	Count mode
31	3 1 0	3 1	Frequency track A
32	3 2 0	3 2	Frequency track B
33	3 3 0	3 3	Input logic
34	3 4 0	3 4	Function control input 1 (terminal 9)
35	3 5 0	3 5	Reaction time control input 1
36	3 6 3	3 6	Function control input 2 (terminal 10)
38	3 8 0	3 8	Adoption of presets P1,P2 and SC
40	4 0 0	4 0	Output logic of digital output
41	4 1 t 1 0.2 5	4 1	Output time preset P1
42	4 2 t 2 0.2 5	4 2	Output time preset P2
43	4 3 0	4 3	Time range of hour counter
44	4 4 0	4 4	Rapid preset recognition
50	5 0 C o d 0	5 0	Code
51	5 1 0	5 1	Baud rate
52	5 2 0	5 2	Parity
53	5 3 0	5 3	Stop bits
54	5 4 0	5 4	Identifier
55	- - - - -		Separating line

## 9. Programming plan

<b>Line 11-17</b>	<b>Status lines 1-7</b>	<b>Line 36</b>	<b>Functionality control input 2 (terminal 10)</b>
0	Parameter enabled for programming	0	Reset static
1	Delete resp. Input lock	1	Reset edge-triggered
2	Skip parameter	2	Reset totalizer edge-active
<b>Line 21</b>	<b>Operating mode</b>	3	Stop
0	Adding (reset to SC)	4	Hold
1	Subtracting (reset to P2)	5	Programming lock
2	Subtracting; but output contact at SC, automatic reset at 0	6	Key lock
<b>Line 22</b>	<b>Preset mode</b>	7	Print
0	Step preset	8	Outputs OUT (P1,P2)
1	P1-trailing preset	<b>Line 38</b>	<b>Adoption of presets P1,P2,SC</b>
<b>Line 23</b>	<b>Reset</b>	0	Immediately effective
0	With automatic reset	1	Upon reset
1	w/o automatic reset	<b>Line 40</b>	<b>Output logic of digital outputs</b>
<b>Line 24</b>	<b>Decimal point in PC, P1, P2, tot, SC</b>	0	Both outputs normally closed
0	None	1	P1 normally open, P2 normally closed
1	0000.0	2	P1 normally closed, P2 normally open
2	000.00	3	Both outputs normally open
3	00.000	<b>Line 41</b>	<b>Output time P1</b>
<b>Line 30</b>	<b>Count mode</b>	0.25	Default
0	Track A UP/DOWN signal at B where required	0.01	Min.
1	Subtracting (A-B)	99.99	Max.
2	Adding (A+B)	<b>Line 42</b>	<b>Output time P2</b>
3	Track A 90° B Single evaluation	0.25	Default
4	Track A 90° B Double evaluation	0.01	Min.
5	Track A 90° B Quadruple evaluation	99.99	Max.
6	Hour counter with preset	<b>Line 43</b>	<b>Time range hour counter</b>
7	Same as 6 but with start and stop	0	999s 99/100s
<b>Line 31</b>	<b>Frequency track A</b>	1	99min 59s 9/10s
0	10 kHz	2	999min 59s
1	25 Hz	3	999h 59min
2	3 Hz	<b>Line 44</b>	<b>Rapid preset recognition</b>
<b>Line 32</b>	<b>Frequency track B</b>	0	Standard
0	10 kHz	1	Rapid
1	25 Hz	<b>Line 50</b>	<b>Code</b>
2	3 Hz	0000	Code not active
<b>Line 33</b>	<b>Input logic</b>	:	
0	PNP Trigger threshold 6 V	9999	
1	NPN Trigger threshold 6 V	<b>Line 51</b>	<b>Baud rate</b>
2	PNP Trigger threshold 3 V	0	4800 Baud
3	NPN Trigger threshold 3 V	1	2400 Baud
<b>Line 34</b>	<b>Functionality control input 1 (terminal 9)</b>	2	1200 Baud
0	Reset static	3	600 Baud
1	Reset edge-triggered	<b>Line 52</b>	<b>Parity</b>
2	Reset totalizer edge-triggered	0	Even Parity
3	Stop	1	Odd Parity
4	Hold	2	No Parity
5	Programming lock	<b>Line 53</b>	<b>Stop bits</b>
6	Key lock	0	1 Stop bit
7	Print	1	2 Stop bits
8	Outputs IN (P1,P2)	<b>Line 54</b>	<b>Identifier</b>
9	Outputs IN (P1,P2) and reset fl.	00	Default
<b>Line 35</b>	<b>Reaction time of control input 1</b>	00	Min.
0	30 ms	99	Max.
1	100 µs		